

How to install Android Apps


IAdea Support
support@iadea.com
Apr-2013

Applicable products

- ▶ XMP-2200/2300/2400
- ▶ XDS-1060/1062/1068
- ▶ XOP-2300


Enter Android system

- ▶ At Basic Settings, click "Advanced" to enter screen below, then click on the "lower right corner" 3 times using the mouse.




Find AppInstaller

- ▶ Click on a tiny icon on upper right corner on the Android desktop.



Run AppInstaller

- ▶ Click on the AppInstaller icon to run this app.



Locate the drive with the app

- ▶ Copy the app onto an USB thumb drive or SD Card, insert it into signboard, then locate it in AppInstaller.

